

Windows 10 Driver Installation

Open web browser go to: <https://abc-officesolutions.com/>

Click go under Download drivers

Enter model number from front of machine E.g. MP2554 IMC3000 ETC

Click the model under drivers , agree to licence agreement

Click download on pcl 6 driver make note of file name

Once downloaded Click file then click UNZIP ,OK , CLOSE

To install printer

Click windows start button

Type control panel (Option will appear as typing)

Click Control panel

Click devices and printers

AT top of window Click add a printer

At the bottom of the window that pops up click the printer that I want isn't listed

Click add a local printer or network printer with manual settings (bottom option)

Click next ,create new port

In box choose standard ip address enter ip from machine *(instructions on finding ip address)

EXAMPLE. 192.168.1.55

Uncheck query printer box ,Click next

Additional port information required Click NEXT (leave on GENERIC)

Install the Driver

Click: have Disk ,BROWSE

Change folder to c:\temp\ZXXXX\disk 1\oemsetup.inf (xxxx = file name noted earlier)

Click ok ,Ricoh

Select your model from the printer list

Click next

Printer sharing : do not share printer Click Next

Print a test page , Click finish

*Ip address Retrieval From machine

Press User tools/counter

System settings

Interface settings

Under machine ipv4 address

Note ip address 192.168.xxx.xxx